



This update is incompatible with Prometheus (Safety Datasheet Software) versions earlier than version 1.4.4.2. If your Prometheus version is earlier than version 1.4.4.2 you must update Prometheus to a minimum of that version **BEFORE** running this update. Note that after updating Prometheus to version 1.4.4.2 this update must then be run before using Harmoneus again.

*NB: If you do not use Prometheus a different upgrade path is required - Please contact Hibiscus PLC for advice.*

### **Purpose of Update:**

1. Add advice on German Water Hazard Classification (WGK) - When importing data for a substance in a preparation from the CLP list, data for are also imported from the German WGK list if the substance is listed. The imported values for ingredients and the recommended value for the product are included when you export a session to Prometheus.
2. Ordering of P phrases on the supply label advice form now depends on whether or not the product will be used by members of the public.
3. The menu items to display mixture and substance forms are not now active if no session is running.
4. The version of the rulebase is now checked when the program starts up and the program will not run if the version and program are incompatible.
5. Allow deletion of constituents from mixtures when running a session for a mixture of mixtures.
6. Option added to disable automatic substring searches. If "Require asterisks for substring searches" is ticked the software will conduct a substring search only when the asterisk character (\*) is included in the search data (to mark the location of the variable content). Not that searching will be faster if this option is selected.
7. Acute toxicity data were now included in export Prometheus (previously omitted by oversight).
8. An error has been corrected which could cause hazard categories to be ignored when the data for a substance in a mixture of mixtures had originally been entered through Prometheus.
9. Untidy spacing of constituent panels when you are listing constituents for mixtures of mixtures has been corrected.

### **Client Update:**

Required for each Harmoneus client.

1. Run the update exe (HHM2-01040008.exe) with administrator rights. You will be asked to enter a passkey (obtain from Hibiscus PLC IT support) then the location of your Harmoneus installation (accept the default if your software was installed into the default location).
2. The update program will test whether Harmoneus is installed at the location given before proceeding. If not the update will fail, but your existing installation will be unaffected. If found the update will proceed.
3. The client will be updated.
4. Once the update is finished, just click [close] to close the updater program.