



This update is incompatible with Harmoneus2 (Classification Software) versions earlier than version 1.4.0.8. If you are using Harmoneus2 in conjunction with Prometheus you will need to upgrade that software to version 1.4.0.8 (minimum) before you can use it again after running this update.

### **Purpose of Update:**

1. # \$ phrases have been added for German Water Hazard Classification (WGK). They are listed automatically with phrases you can select for a substance in section 3, for inclusion in section 12.6, and for inclusion in section 15.1.
2. Option added to disable automatic substring searches. If "Require asterisks for substring searches" is ticked the software will conduct a substring search only when the asterisk character (\*) is included in the search data (to mark the location of the variable content). Note that searching will be faster if this option is selected.
3. An error that meant the properties of all substances in section 3 except the first one appeared in the wrong language when a datasheet was transposed to a different template and language has been corrected.

### **Server Update:**

*NB: The server update will make changes to your database. Before making these changes you will be prompted to make a backup. As the changes on this occasion are quite extensive it is especially important to take the extra time to make the backup in case any problems occur. Depending on the speed of your system, this update may require many minutes to run.*

Always perform the server update *before* the clients.

1. Ensure all Harmoneus2 and Prometheus users are logged out of the respective softwares (these softwares share the Prometheus Database). Note that both Prometheus and Harmoneus clients must also be updated before they may safely be used again.
2. Run the server update exe (HPRM-01040402svr.exe) with administrator rights. You will be asked to enter a passkey (obtain from Hibiscus PLC IT support) then the location of your Prometheus installation (accept the default if your software was installed into the default location).
3. The update program will test whether Prometheus is installed at the location given before proceeding. If not the update will fail, but your existing installation will be unaffected. If found the update will proceed.
4. The update program will next check to see which version of the database you are currently running and will then apply all applicable patches to bring it fully up to date. Note that if you have skipped any previous updates there may be a number of these patches to apply and each may take a few minutes. If the program cannot determine the current database version, it will attempt to apply all patches – some of which may fail if they have already been applied (just cancel the error – do not restore – and let the program try the next patch).
5. As it runs each patch, the update program will display a login page for your database. Check the details are correct then click on [Next] to connect to the database. You will then be prompted to make a backup. Depending on the size of your database this backup may take many minutes to complete. It is not necessary to create a backup before every patch where multiple patches are applied, but we highly recommend that you take the extra time to make a backup before the first patch is applied so that you have a copy from before any alterations are made. After the backup is completed the program will proceed to apply the patch - just click on the [Finish] button to continue. If further patches are required to bring your database fully up to date this procedure will repeat.



## Prometheus2

Software Release Notes: ver 1.4.0.08

6. Once all patches have been applied, click close to close the updater program.

*If you would prefer a Hibiscus representative to perform the server update on your behalf by remote login then please call our IT department on 0113 2031950, or email [support@hibiscus-plc.com](mailto:support@hibiscus-plc.com), to arrange an appointment. Computer must have an internet connection – check with you IT to see if remote connection is allowed at your site.*

### **Client Update** (Prometheus):

Required for each client (not server unless performing a client-only update)

1. Run the client update exe (HPRM-01040402cln.exe) with administrator rights. You will be asked to enter a passkey (obtain from Hibiscus PLC IT support – note this is the same as for the server update) then the location of your Prometheus installation (accept the default if your software was installed into the default location).
2. The update program will test whether Prometheus is installed at the location given before proceeding. If not the update will fail, but your existing installation will be unaffected. If found the update will proceed.
3. The client will be updated.
4. Once the update is finished, just click close to close the updater program.